



Fudo Enterprise 5.6 - Access Gateway Manual

Fudo Security

28.08.2025

1	About documentation	1
2	System overview	2
3	Logging into the Access Gateway	4
4	Secret Checkout and Checkin	6
4.1	Secret Checkout	6
4.2	Secret Checkin	7
5	Displaying passwords history	9
6	Displaying and editing accounts notes	11
7	Establishing connections	13
7.1	Connecting via access request	13
7.2	Connecting over RDP, VNC and SSH in browser	15
7.3	Connecting over RDP on Microsoft Windows 7 and 10	17
7.4	Connecting over RDP on Mac OS X	18
7.5	Connecting over RDP on Ubuntu Linux	21
7.6	Connecting over SSH on Microsoft Windows 7 and 10	22
7.7	Connecting over SSH on Mac OS, Linux	24
7.8	Connecting to a Server with a Port Range	26
8	WebClient Features	28
9	Change Password	31
10	Troubleshooting	32

Conventions and symbols

This documentation is written using the following conventions:

- *italic* - this formatting is used to mark user interface elements.
- **example** - this formatting is used to write example value of a parameter, API method name or code example.
- Note field:

Note: Note field usually contains additional information closely related with described topic, e.g. suggestion concerning given procedure step; additional conditions which have to be met.


- Warning field:

Warning: Warning field usually contains essential information concerning system's operation. Not adhering to this information may have irreversible consequences.

CHAPTER 2

System overview

Access Gateway enables initiating connections with monitored servers available for the logged-in user.



The Access Gateway also allows:

- taking an account password and automatically giving it back after a specified timeout.

Note: More information on this under the *Secret Checkout and Checkin* page.

- viewing a password history to selected accounts, managed by FUDO's password vault module.

Note: Check more details at the *Displaying passwords history* page.

- selecting one of the available keyboard layouts:
 - English (US),
 - German,
 - German (Swiss),
 - Norwegian, and
 - Turkish-Q.

Warning: Keyboard layouts are available for connections via RDP protocol in browser only for now.

- setting interface language to English, Polish, Russian, Ukrainian or Kazakh.

Note: Availability of the particular language is specified in the license.

Related topics:

- *Logging into the Access Gateway*
- *Secret Checkout and Checkin*
- *Displaying passwords history*
- *Displaying and editing accounts notes*
- *Establishing connections*
- *Change Password*
- *Troubleshooting*

Logging into the Access Gateway


Note:

- Access Gateway is compatible with the following web browsers:
 - Google Chrome, Mozilla Firefox, Internet Explorer for Microsoft Windows.
 - Google Chrome, Mozilla Firefox for Ubuntu.
 - Google Chrome, Mozilla Firefox, Safari dla systemu operacyjnego Mac OS X.
 - *Access Gateway* supports Single Sign On for Active Directory accounts. Refer to system documentation for information on how to enable the SSO in Access Gateway.
 - *Access Gateway* also allows login in with Azure or Okta profile. An authorized administrator can set the OpenID Connect globally for the whole system instance.
-

1. Open web browser and direct it to the IP address of the Access Gateway.
-

Note: You can obtain the IP address from your system administrator.

2. Accept the security alert exception to display the login page.
 3. Enter the username, password and click *LOGIN*.
-

The image shows a web-based login interface for FUDO. At the top, there is a dark blue header bar with the word "FUDO" in white, bold, uppercase letters. Below the header, the background is a light gray. In the center of the page, the word "LOGIN" is displayed in bold, black, uppercase letters. Underneath "LOGIN", there are two input fields: the first is labeled "Username:" and the second is labeled "Password:". Both labels are in a small, black, sans-serif font. Below the password field, there is a blue rectangular button with the word "Login" in white, centered text.

Related topics:

- *Connecting over RDP on Mac OS X*
- *Connecting over RDP on Ubuntu Linux*


Secret Checkout and Checkin

An account secret can be temporarily taken by the authorized user and given back after their work is done. The user takes the password by sending a request for the secret *checkout*. Then, the secret is given back by the user’s manual *checkin* or if the administrator set the duration for the user, the secret is returned automatically after that time is over.


4.1 Secret Checkout

Follow the steps to *checkout* the account secret:

- 1. Find an account whose password you want to take, hover mouse on it to display more options.
- 2. Click the  icon.




- 3. Click *SUBMIT*.

**Note:**

- Prompt for password checkout reason is optional for the safe configuration.
- Depending on the configuration, password checkout may require system administrator's approval.
- If the password is currently taken by the other user, wait until it's returned or use the *FORCE CHECKOUT* option.

4. Click:

- *Show password* to disclose the password, or.
- *Copy password* to copy the password to system clipboard.




4.2 Secret Checkin

Follow the steps to *checkin* the account secret:

1. Find an account whose password you want to give back, hover mouse on it to display more options.
2. Click the  icon.

or

click the  icon to open the Checkout modal window and click  Checkin.




Related topics:

- *Displaying passwords history*


Displaying passwords history

Account password may be changed manually by the user, or automatically by the Fudo Enterprise system, based on the given settings and with given frequency. It is possible to see how and when the password was changed. Follow the steps to do so:

- 1. Find account which passwords history you want to view.
- 2. Click *Password history* drop-down list.



- 3. Choose the timeline when the password had been changed.



4. Click  to view selected password.

Related topics:


- *[Change Password](#)*

Displaying and editing accounts notes

Notes are created by the system administrator and they provide additional information on server access.

Note: Notes access is granted by the system administrator on *safe* object level. Depending on system settings, users can access notes in read-only or read and write modes.

1. Find account which note you want to access, hover mouse on it to display more options.
2. Click a comment icon to open the note.



3. Add or edit the note and click *SAVE NOTE* to store changes. Click on the Cancel button on the upper right corner or press the *Esc* key on your keyboard to close the modal without

changes.

Note: Notes' editing requires *write* access right assigned by the system administrator.

Establishing connections

7.1 Connecting via access request

You can send a request for access to the resources via the Access Gateway. There are available two types of the access requests: immediate and scheduled.


Immediate requests can be set from now up to the next 24 hours. When an immediate request is sent, its access time starts when the request is accepted. Then, you have 24 hours to start your session. When you start the session, the system counts the session time, which was requested, and terminates connection when the requested session time is over. If you do not use the access and do not connect for 24 hours after access is granted, the access becomes expired.

The scheduled type of requests requires selecting a time period in the future, including exact time and date.

7.1.1 Sending access request

In order to send a request, follow the steps:

1. Hover the mouse over the particular account to see more options.
2. Click the *Access request* button.



3. Select a type of the request: immediate or scheduled.

Note: For both types of requests, the Reason field is required in order to activate the sending.

4. Define the request time.

The screenshot shows the Fudo web interface with the 'Requestable' tab selected. The account name is 'jit-test', the protocol is 'HTTP', the server name is 'jit-test-http', and the server host is '10.0.2'. The request type is set to 'Immediate' (highlighted with a blue border). The time is set to '2h' on a slider ranging from 0h to 24h. The reason field is empty, and the 'SEND REQUEST' button is visible at the bottom right.

The screenshot shows the Fudo web interface with the 'Requestable' tab selected. The account name is 'forward-Windows', the protocol is 'RDP', the server / pool name is 'Windows servers', and the host/mask/port is 'windows.example.org:3389'. The request type is set to 'Scheduled' (highlighted with a blue border). The date range is set from '1/12/2022 09:42' to '31/12/2022 00:00'. The reason field is empty, and the 'Send request' button is visible at the bottom right.


5. Click the *Send request* button.

7.1.2 Watching request status

You can receive 2 types of e-mail notifications about your request:

- **Access Request accepted** - the request was approved by the required amount of the administrators.
- **Access Request rejected** - the request was denied.

Status of the pending requests, as well as the requests history, are available under the *Requests* drop-down list having a mouse over the account.



Here you can observe the process of voting, including seeing a number of required votes and how much voices is left for access to be granted.

Requests					New request
Time	Value	Status	Reason		
Fr, July 30th 2021, 10:26	2h	EXPIRED	Test2	Votes 0/1	▼
Fr, July 30th 2021, 10:26	2h	EXPIRED	Test	Votes 0/1	▼
Tu, July 13th 2021, 9:13	2h	EXPIRED	Try again	Votes 1/2	▲
			granted by admin	We, April 14th 2021, 3:59	ok
Tu, July 13th 2021, 9:13	2h	REJECTED	g	Votes 1/1	▼
We, April 14th 2021, 16:55	2h	REVOKED	Try	Votes 1/1	▼

Note: When the access has been already granted, the user can send another request from the requests history bar by selecting the *+ New request* button.

7.2 Connecting over RDP, VNC and SSH in browser

Connecting over RDP, VNC and SSH in browser is available via the Webclient feature. Filter the Webclient-supported accounts by choosing the *Webclient* tab.

Note: Connecting to the server over **RDP protocol** in browser, select one of the available keyboard layouts:

- *English (US)*,
- *German*,
- *German (Swiss)*,
- *Norwegian*, and
- *Turkish-Q*.

Follow the steps to use the Webclient feature for RDP, VNC or SSH connection:

1. Find desired account and server, hover your mouse over to display more options.
2. Click the *Web client* button next to the account you want to use to connect to the server.

FUDO

?

ONLINE HELP

tpovar

AllRequestableWebclient

Account name

Protocol

Server name

Host:Port

Native client

Web client

Administrator@remot... RDP

Windows 2019 RDP QA107

10.0.23

Webclient

root@ubuntu

SSH

Ubuntu 18 SSH Static single

10.0.23

Webclient

<1>


Note: Each session is opened in a separate browser tab.

7.2.1 Providing a Login Reason in an RDP Session

If an RDP session is initiated using an account added to a Safe with the *Login reason* option enabled, the user will be prompted to provide a reason before logging in to the target system.

Pasting the Login Reason Text From the Clipboard:

To simplify entering the login reason, you can use the **Clipboard** feature available in the top-right corner of the User Portal interface.



1. Click the clipboard icon in the top-right corner of the screen.
2. Paste or type the text you want to use as the login reason.
3. Click the **Copy** button to move the text to the session clipboard.
4. Go to the field where the login reason must be entered.
5. To paste the text, **right-click** in the input field.

Note: Keep in mind that the clipboard has a character limit for the **Login reason** field: a maximum of **60 characters** for Polish and English text, and **40 characters** for Cyrillic. If


the copied text exceeds this limit, it may be truncated or not copied at all.

Related topics:

- [WebClient Features](#)
- [Connecting over RDP on Mac OS X](#)
- [Connecting over RDP on Microsoft Windows 7 and 10](#)
- [Connecting over RDP on Ubuntu Linux](#)

7.3 Connecting over RDP on Microsoft Windows 7 and 10

1. Find desired account and server, hover your mouse over to show more options.
2. Select the *Native client* button.



3. Choose the listener, via which you want to connect.




4. Click *Connect*.


Note:

- *Google Chrome* will automatically save the file.

- Select the *Always open this file type* option to automatically start the client app.



5. Click *Continue* in the credentials prompt window without providing the password.




6. Click *Continue* to connect to the server despite the certificate alert.

Related topics:


- [Connecting over RDP on Mac OS X](#)
- [Connecting over RDP on Ubuntu Linux](#)

7.4 Connecting over RDP on Mac OS X

Note: To establish RDP connections on Mac OS X, download and install *Microsoft Remote Desktop*.



1. Find desired account and server, hover your mouse over to show more options.
2. Select the *Native client* button.




3. Choose the listener, via which you want to connect.




4. Click *Connect*.

Note:

- *Google Chrome* will automatically save the file.
- Select the *Always open this file type* option to automatically start the client app.



5. Click *Continue* to accept the certificate and initiate connection with selected server.




Related topics:

- *Connecting over RDP on Microsoft Windows 7 and 10*
- *Connecting over RDP on Ubuntu Linux*

7.5 Connecting over RDP on Ubuntu Linux

Note: Establishing RDP connections on Ubuntu 16.04 LTS requires installing `xfreerdp`. Execute `sudo apt-get install freerdp-x11`, to install it before proceeding with connecting over RDP protocol.

1. Find desired account and server, hover your mouse over to show more options.
2. Select the *Native client* button.



3. Choose the listener, via which you want to connect.
4. Copy generated string.



5. Execute command in terminal window.

Related topics:

- *Connecting over RDP on Mac OS X*
- *Connecting over RDP on Microsoft Windows 7 and 10*

7.6 Connecting over SSH on Microsoft Windows 7 and 10

Note: To automatically initiate SSH connections you must install *PuTTY* and configure association between client the app and the SSH protocol. To do the latter it is advised to install *WinSCP*, which will perform necessary configuration changes. Both programs must be in their 32-bit versions.

1. Download and install *WinSCP*.

<https://winscp.net/download/WinSCP-5.19.2-Setup.exe>


Note: Verify the checksum value to make sure that the integrity of the binary file has not been compromised.

2. Download and install *PuTTY*.


<https://winscp.net/download/putty-0.75-installer.msi>

Note:

- Install *PuTTY* in the default installation location: C:\Program Files (x86)\PuTTY\.
- During installation select default features set.




3. Log in to the Access Gateway.
4. Find desired account and server, hover your mouse over to show more options.
5. Select the *Native client* button.



6. Choose the listener, via which you want to connect.



7. Click *Connect* to launch client application appropriate for selected listener with connection parameters forwarded.
8. In the *Launch application* select *WinSCP:SFTP,FTP,WebDAV and SCP* and click *Open*.
9. The connection has been established.



```

10.0.60.1 - PuTTY
Using username "74f6adec-79b3-d384-1f25-f0b735960e42".
Last login: Mon Apr 10 13:32:08 2017 from 10.0.60.105
FreeBSD 11.0-STABLE (GENERIC) #0 r313108: Fri Feb  3 01:46:57 UTC 2017

Welcome to FreeBSD!

Release Notes, Errata: https://www.FreeBSD.org/releases/
Security Advisories:  https://www.FreeBSD.org/security/
FreeBSD Handbook:    https://www.FreeBSD.org/handbook/
FreeBSD FAQ:         https://www.FreeBSD.org/faq/
Questions List:      https://lists.FreeBSD.org/mailman/listinfo/freebsd-questions/
FreeBSD Forums:      https://forums.FreeBSD.org/

Documents installed with the system are in the /usr/local/share/doc/freebsd/
directory, or can be installed later with:  pkg install en-freebsd-doc
For other languages, replace "en" with a language code like de or fr.

Show the version of FreeBSD installed:  freebsd-version ; uname -a
Please include that output and any error messages when posting questions.
Introduction to manual pages:  man man
FreeBSD directory layout:     man hier

Edit /etc/motd to change this login announcement.
root@freebsd01:~ #


```

Related topics:

- *Connecting over RDP on Mac OS X*
- *Connecting over RDP on Microsoft Windows 7 and 10*
- *Connecting over RDP on Ubuntu Linux*

7.7 Connecting over SSH on Mac OS, Linux


1. Find desired account and server, hover your mouse over to show more options.
2. Select the *Native client* button.



3. Choose the listener, via which you want to connect.



4. Click *Connect*.
5. Click *Allow* to open the Terminal.



6. The connection has been established.

**Related topics:**


- *Connecting over RDP on Mac OS X*
- *Connecting over RDP on Microsoft Windows 7 and 10*
- *Connecting over RDP on Ubuntu Linux*

7.8 Connecting to a Server with a Port Range

Native Client

After hovering over the account you want to use for the connection and selecting the Native Client option, follow these steps:


1. Select from the dropdown list the address of the server with a port range that you want to connect to (in case of a server pool).
2. In the **Port** field, enter a port selected from the range specified during the configuration of the given server.
3. Click the **Use** button.
4. Click the **Connect** button to retrieve or obtain the connection details for the appropriate server protocol.



Web Client

After hovering over the account you want to use for the connection and selecting the Web Client option, follow these steps:

1. Select from the dropdown list the address of the server with a port range that you want to connect to (in case of a server pool).
2. In the **Port** field, enter a port selected from the range specified during the configuration of the given server.
3. Click the **Connect** button to establish a connection in the browser.




Related topics:

- *Connecting over RDP on Mac OS X*
- *Connecting over RDP on Microsoft Windows 7 and 10*
- *Connecting over RDP on Ubuntu Linux*

WebClient Features

For the sessions based on RDP and SSH protocols carried out in the browser panel tab has embedded the following features:


- *Hide / Show* button that minimizes / maximizes the connection window.
- Session tabs displaying protocol type, listener name and connection status:
 -  connection is establishing,
 -  session is connected,
 -  session is disconnected.
- “Clipboard” button that allows to copy the text to the server’s system clipboard. Just paste the text into the clipboard window and press *Copy*.



Note: Hovering over a particular tab shows the preview of the session.


For connections established using the RDP protocol additionally you can use:

- *Screen resizing* button - available during connections where a specific resolution is set in the Safe's "Protocol Functionality" settings. When enabled, the WebClient screen is scaled automatically with the browser size change.
- *On-screen keyboard* feature button.



Additionally, for the sessions based on SSH protocol, there are features that allow customizing the view. You can change font size and a terminal color scheme. Four themes are available:

- black-white - default scheme,
- gray-black,
- green-black,
- white-black.



Note: Access Gateway saves tabs with recent connections established via the WebClient. Sessions that were left in the opened tabs are saved and can be reconnected by a user by clicking on the particular session tab.

Related topics:


- *Connecting over RDP, VNC and SSH in browser*
- *Connecting over RDP on Mac OS X*
- *Connecting over RDP on Microsoft Windows 7 and 10*
- *Connecting over RDP on Ubuntu Linux*

Change Password

Fudo Enterprise Access Gateway allows changing a static password as well as a password enabled as a part of multi-factor authentication.

In order to change the password, follow the steps:

1. Click on your login name on the upper right corner.
2. Select the *Change password* button.



3. Follow the displayed messages and provide a new password. Once done, click *Save*.

Related topics:

- *Displaying passwords history*

CHAPTER 10

Troubleshooting

Problem	Symptoms and solution description
Cannot log in to the Access Gateway	Symptoms: • The user cannot log in. Solution: • Make sure you are entering correct login credentials. • Contact system administrator to verify whether you have Access Gateway access privileges. • Contact system administrator to verify the Access Gateway time policy settings.
Accounts list is missing objects.	Solution: • Contact your system administrator to make sure you have access to required safes. Symptoms: • Cannot connect to selected server. Reason: connection takes place outside the timeframe defined by the access time policy. Solution: contact system administrator to verify your time policy settings.